Instalación Driver HP UPD PCL6 v7.0.1

Ricard Fdez. 07/03/2023

Descargar driver de hp.com/go/upd: <u>https://ftp.hp.com/pub/softlib/software13/COL40842/ds-99374-24/upd-pcl6-x64-7.0.1.24923.exe</u>

## Descomprimir driver **SIN** instalar:

	Name	Date modified	Туре	Size
	Drivers	19/05/2022 10:47	File folder	
1	hpbcfgre.dll	25/03/2021 8:12	Application extens	4.761 KB
*	hpbuio32.dll	25/03/2021 8:12	Application extens	1.172 KB
s A	hpbuio64.dll	25/03/2021 8:12	Application extens	1.505 KB
*	hpbuio200l	25/03/2021 8:12	Security Catalog	404 KB
	hpbuio2001	25/03/2021 1:59	Setup Information	31 KB
	hpbuio200le	25/03/2021 8:12	Security Catalog	403 KB
	hpbuio200le	25/03/2021 1:59	Setup Information	48 KB
	hpbuiodm64.dll	25/03/2021 8:12	Application extens	1.118 KB

## Instalar driver desde Panel de Control:

	-	
· → • ↑	Control Panel	\All Control Panel Items\Devices and Printers
dd a device	Add a printer	

## Seleccionar impresora manualmente:

and the second s	20 Million ( 1980)
an history and the	Reference and the second
REAL PROPERTY AND INCOME.	A 10.007 10.3 or 04020

## Seleccionar Añadir impresora TCP/IP:



Seleccionar **TCP/IP**, introducir IP de la impresora y desmarcar la consulta a impresora:



Indicar que se va a utilizar un driver del disco duro:

Choose your printer from the list. Click Window To install the driver from an installation CD, clic	vs Update to see more models. :k Have Disk.
To install the driver from an installation CD, clic	:k Have Disk.
Manufacturer ^ Printers	,
Generic Generic / Text	Only
HP Generic IBM C	Graphics 9pin
Kyocera Generic IBM C	Graphics 9pin wide
Microsoft Game MS Publisher	Color Printer
Disab Disab	Inconcentration of the second s
	Mundaue Undate Have Dick

# Seleccionar el driver v7.0.1:

Instal	I the printer driver		
	Choose your printer from the list. Cli	ck Windows Update to see more mo	dels.
~	To install the driver from an installation	on CD, click Have Disk.	
Printe	15		
H	Universal Printing PCL 6 (v7.0.1)		
TI	his driver is digitally signed.	Windows Update	Have Disk
-			

Introducir un nombre para mostrar o dejar el que aparece por defecto:

÷	li Add Printer
	Type a printer name
	Printer name: HP Universal Printing PCL 6 (v7.0.1)
	This printer will be installed with the HP Universal Printing PCL 6 (v7.0.1) driver.

Se inicia la instalación del driver (este paso puede tardar unos minutos):

ing A	dd Printer	
	Installing printer	

Finalizada la instalación del paso anterior, seleccionar MO compartir la impresora:

Printer Sharing				
If you want to share this print a new one. The share name w	er, you must provide a share name. You can use the suggested name or typ ill be visible to other network users.			
Do not share this printer	1			
O Share this printer so that o	thers on your network can find and use it			
Share name:	HP Universal Printing PCL 6 (v7.0.1)			
Locationi				
Comment:				

Dejar marcada de impresora por defecto y NO imprimir página de prueba aún:

	II INDUCT INTER PROFESSION
You've successfully	y added HP Universal Printing PCL 6 (V7.0.1)
Set as the default p	printer
To check if your printer i	is working properly, or to see troubleshooting information for the printer, print a
To check if your printer i test page.	s working properly, or to see troubleshooting information for the printer, print a
To check if your printer i test page. Print a test page	is working properly, or to see troubleshooting information for the printer, print a

Tras la instalación del driver UPD, configurar las opciones del driver.

Acceder a **Propiedades** de la impresora con botón derecho y pulsar en la pestaña **Configuración del dispositivo**:



Al seleccionar **Actualizar ahora**, el driver contacta con la impresora para obtener la configuración exacta, este proceso puede tardar unos minutos:

#### Nota: No pulsar en OK tras seleccionar Actualizar ahora.

Impresora: HP Liniversal Printing PCL 6 (v2.0.1)	
Estado:	
Estableciendo comunicación con la impresora	

Localizar en la misma pestaña Job Accounting (contabilidad de trabajos) y seleccionar Habilitado:



Seleccionar la pestaña General y pulsar en Preferencias:

Social	ty	Device	Settings	About
General	Sharing	Ports	Advanced	Color Management
3	HP Univers	sal Printing P	CL 6 (v7.0.1)	
Location:				
Comment:				
Model:	HP Univers	al Printing PC	L 6 (v7.0.1)	
Model: Features	HP Univers	al Printing PC	CL 6 (v7.0.1)	
Model: Features Color: No	HP Univers	al Printing PC	CL 6 (v7.0.1) Paper available:	
Model: Features Color: No Double-sia	HP Univers ded: Yes	al Printing PC	L 6 (v7.0.1) Paper available:	^
Model: Features Color: No Double-sin Staple: No	HP Univers	al Printing PC	IL 6 (v7.0.1) Paper available:	^
Model: Features Color: No Double-sin Staple: No Speed: 45	HP Univers ded: Yes	al Printing PC	L 6 (v7.0.1) Paper available:	^
Model: Features Color: No Double-sii Staple: No Speed: 45 Maximum	HP Univers ded: Yes ppm resolution: 12	al Printing PC	L 6 (v7.0.1) Paper available:	< v
Model: Features Color: No Double-sii Staple: No Speed: 45 Maximum	HP Univers ded: Yes ppm resolution: 12	al Printing PC	L 6 (v7.0.1) Paper available:	^ ~

Seleccionar Job Accounting y configurar las opciones siguientes:

Advanced Printing Shortcut	a Paper/Quality Effects Finishing Job Storage Job Account	ing Services
Your job will be printed wil your printer administrator.	h a job accounting user access code. You need to enter the user ac If you want a prempt prior to printing every job, check " Always prom	ccess code provided by pt when printing".
Accounting Type	User Access Code only ~	
Settings		
User Access Code	123456	
	(4 - 8) numbers	
Always prompt when p	inting	

Nota: <u>El código de acceso debe coincidir con el código de usuario introducido en la impresora</u> mediante el .zip que contiene el .csv modificado.